#### COMP 122/L Lecture 12

Kyle Dewey

#### Outline

- Memory instructions
  - Load (ldr)
  - Store (str)
- Arrays

# Memory Operations

#### Refresher

You've already seen one form of 1 dr for handling strings

#### Refresher

You've already seen one form of 1dr for handling strings

```
.data
my_string:
    .asciz "hello"

.text
ldr r0, =my_string
```

#### Refresher

You've already seen one form of 1dr for handling strings

```
.data
my_string:
    .asciz "hello"

.text
ldr r0, =my_string

Puts starting address of "hello" in r0
```

# Putting Integers in Memory

.word directive will put a 32-bit integer in memory, much like .asciz will put a string in memory

# Putting Integers in Memory

.word directive will put a 32-bit integer in memory, much like .asciz will put a string in memory

```
.data
my_string:
    .asciz "hello"
first_int:
    .word 42
second_int:
    .word 38
```

Step I: use ldr to put its address into a register...

Step I: use ldr to put its address into a register...

```
.data
first int:
  .word 42
second int:
  .word 38
  .text
ldr r0, =first int
```

Step 2: use 1dr with [] to read the value at the address

```
.data
first_int:
   .word 42
second_int:
   .word 38

.text
ldr r0, =first int
```

Step 2: use ldr with [] to read the value at the address

```
.data
first int:
  .word 42
second int:
  .word 38
  .text
ldr r0, =first int
ldr r1, [r0]
```

Step 2: use ldr with [] to read the value at the address

```
.data
first_int:
    .word 42
second_int:
    .word 38
```

```
.text
ldr r0, =first_int
ldr r1, [r0]
```

Step I: use 1dr to put its address into a register...

Step I: use ldr to put its address into a register...

```
.data
first_int:
   .word 42
second_int:
   .word 38

.text
ldr r0, =first_int
```

Step 2: use str to write a value at that address

```
.data
first_int:
   .word 42
second_int:
   .word 38

.text
ldr r0, =first_int
```

Step 2: use str to write a value at that address

.data

```
first int:
  .word 42 57
second int:
  .word 38
  .text
ldr r0, =first int
mov r1, #57
str r1, [r0]
```

### Example:

memory variables.s

# Arrays

# Specifying Arrays

Only distinction from variables: multiple values are specified with the .word directive

# Specifying Arrays

Only distinction from variables: multiple values are specified with the .word directive

```
.data
first_int:
.word 42
```

# Specifying Arrays

Only distinction from variables: multiple values are specified with the .word directive

```
.data
first_int:
   .word 42
array:
   .word 32, 65, 76, 87
```

```
.data
arr:
  .word 32, 65, 76
  .text
ldr r0, = arr
ldr r1, [r0]
add r0, r0, #4
ldr r2, [r0]
add r0, r0, #4
ldr r3, [r0]
```

```
.data
arr:
  .word 32, 65, 76
  .text
ldr r0, = arr
                  r1: 32
ldr r1, [r0]
add r0, r0, #4
                  r2: 65
ldr r2, [r0]
add r0, r0, #4
                  r3: 76
ldr r3, [r0]
```

```
32
                                        76
                                65
  .data
arr:
                      arr | arr + 4 | arr + 8
  .word 32, 65, 76
  .text
ldr r0, = arr
                  r1: 32
ldr r1, [r0]
add r0, r0, #4
                  r2: 65
ldr r2, [r0]
add r0, r0, #4
ldr r3, [r0]
```

#### Example:

register\_indirect.s

## More on Memory Access

ldr r3, [r0]

- The above instruction uses the register indirect addressing mode
  - Addressing mode: how the processor accesses something
  - Register indirect: Memory access is done through an address in a register
- Many more available: see register\_\*.s

#### Array Access Example:

print array fixed length.s

# Writing to Array Example:

write array increasing.s

# Another Array Access Example:

print array variable length.s